

ASCII via ComPort

Courier New 10 blue Numbers Signs # 000-032 True ASCII

000 NUL	016 DLE	032 SP	048 0	064 @	080 P	096 `	112 p
001 SOH	017 XOH	033 !	049 1	065 A	081 Q	097 a	113 q
002 STX	018 DC2	034 "	050 2	066 B	082 R	098 b	114 r
003 ETX	019 XOF	035 #	051 3	067 C	083 S	099 c	115 s
004 EOT	020 DC4	036 \$	052 4	068 D	084 T	100 d	116 t
005 ENQ	021 NAK	037 %	053 5	069 E	085 U	101 e	117 u
006 ACK	022 SYN	038 &	054 6	070 F	086 V	102 f	118 v
007 BEL	023 EOB	039 '	055 7	071 G	087 W	103 g	119 w
008 BS	024 CAN	040 (056 8	072 H	088 X	104 h	120 x
009 HTB	025 EOM	041)	057 9	073 I	089 Y	105 i	121 y
010 LF	026 SUB	042 *	058 :	074 J	090 Z	106 j	122 z
011 VTB	027 ESC	043 +	059 ;	075 K	091 [107 k	123 {
012 FF	028 SPF	044 ,	060 <	076 L	092 \	108 l	124
013 CR	029 SPG	045 -	061 =	077 M	093]	109 m	125 }
014 SHO	030 SPR	046 .	062 >	078 N	094 ^	110 n	126 ~
015 SHI	031 SPU	047 /	063 ?	079 O	095 _	111 o	127 □
128 e	144 □	160	176 °	192 Á	208 Ð	224 à	240 ò
129 □	145 \	161 i	177 ±	193 Ă	209 Ñ	225 á	241 ñ
130 ,	146 /	162 ç	178 ²	194 Ā	210 Ò	226 â	242 ó
131 f	147 "	163 Ę	179 ³	195 Ă̄	211 Ó	227 ã	243 ô
132 "	148 "	164 ×	180 ´	196 Ą	212 Ő	228 ä	244 ö
133 .	149 •	165 Ÿ	181 µ	197 Ȧ	213 Ő̄	229 å	245 ø
134 †	150 —	166 †	182 ¶	198 Ě	214 Ő̄̄	230 æ	246 ȳ
135 ‡	151 —	167 ‡	183 ·	199 Ć	215 ×	231 ç	247 ÷
136 ^	152 ~	168 ·	184 ¸	200 Ě̄	216 Ø	232 è	248 ø
137 %	153 ®	169 ©	185 ¹	201 Ě̄̄	217 Ù	233 é	249 ù
138 š	154 š	170 *	186 º	202 Ě̄̄̄	218 Ú	234 ê	250 ú
139 <	155 >	171 ‹	187 »	203 Ě̄̄̄̄	219 Û	235 ë	251 û
140 €	156 €	172 —	188 ¼	204 Ě̄̄̄̄̄	220 Ü	236 ì	252 ü
141 □	157 □	173 —	189 ½	205 Ě̄̄̄̄̄̄	221 Ý	237 í	253 ý
142 Ž	158 Ž	174 @	190 ¾	206 Ě̄̄̄̄̄̄̄	222 Ě	238 î	254 ì
143 □	159 Y	175 —	191 ̂	207 Ě̄̄̄̄̄̄̄̄	223 ß	239 ï	255 y

000 NUL
001 Start Of Header
002 Start Of Text
003 End Of Text
004 End Of Transmission
005 Enquiry
006 Acknowledge
007 Bell
008 Backspace
009 Horizontal Tab
010 Line Feed
011 Vertical Tab
012 Form Feed
013 Carriage Return
014 Shift Out
015 Shift In
016 Dataline Escape
017 DC1 (XOH)
018 DC2
019 DC3 (XOFF)
020 DC4
021 Negative Acknowledge
022 Synchronous Idle
023 End Of Transmission Block
024 Cancel
025 End Of Medium
026 Substitute
027 Escape
028 File Separator
029 Group Separator
030 Record Separator
031 Unit Separator
032 Space (Blank)

Asc(Mid(txtS,I,1))
255 [Color bars]

Send current sign continuously
Stop sending the sign
Hide background

Set form position 878 Top
Set form center 6075 Left

Signs to be send via TxD
Time [ms] between the signs

TxD Send Port open
 RxD Receive Port closed

Com1 Man New Exit Send

VB6-Programmoberfläche "RS232 Send Receive.exe"